


Drafting the Sleeve Basic Pattern

Get one-fourth sheet of pattern paper. Construct a sleeve.
Place the centerline on a folded pattern paper.



basic sleeve pattern

- 1-2 = sleeve length $7 \frac{1}{2}$ inches (19 cm) to $7 \frac{3}{4}$ inches (20cm)
- 1-3 = $4 \frac{1}{2}$ inches (12 cm)
- Square points 3 and 2 to the right
- 1-4 = $\frac{3}{8}$ inch (1 cm)
- 4-5 = $\frac{1}{2}$ armhole measure
- 2-6 = $\frac{1}{2}$ lower arm girth + $\frac{3}{8}$ inch (1 cm)
- Connect 5 to 6 and 4 to 5
- Divide line 4-5 into 4 equal parts and mark 7, 8, 9
- 7-10 raise $\frac{5}{8}$ inch (1.5 cm)
- 9-11 lower $\frac{5}{8}$ inch (1.5 cm)
- Connect 4, 10, 8 with a French curve
- Connect 5, 12, 8 with a French curve (for front sleeve cap)
- 8-12 = $\frac{1}{4}$ inch (0.5 cm).
- 13 – center of 11 and 9
- Connect 10, 12, 13, and 5 for back sleeve capline with a dotted line

basic sleeve pattern

- 1-2 = sleeve length $7\frac{1}{2}$ inches (19 cm) to $7\frac{3}{4}$ inches (20cm)
- 1-3 = $4\frac{1}{2}$ inches (12 cm)
- Square points 3 and 2 to the right
- 1-4 = $\frac{3}{8}$ inch (1 cm)
- 4-5 = $\frac{1}{2}$ armhole measure
- 2-6 = $\frac{1}{2}$ lower arm girth + $\frac{3}{8}$ inch (1 cm)
- Connect 5 to 6 and 4 to 5
- Divide line 4-5 into 4 equal parts and mark 7, 8, 9
- 7-10 raise $\frac{5}{8}$ inch (1.5 cm)
- 9-11 lower $\frac{5}{8}$ inch (1.5 cm)
- Connect 4, 10, 8 with a French curve
- Connect 5, 12, 8 with a French curve (for front sleeve cap)
- 8-12 = $\frac{1}{4}$ inch (0.5 cm).
- 13 – center of 11 and 9
- Connect 10, 12, 13, and 5 for back sleeve capline with a dotted line
- Cut off in the dotted line for back sleeve pattern
- Cut off 12 to 5 and 6 to 5
- Open the sleeve and cut 5, 11, 8 to 10 for front sleeve pattern

After drafting the basic pattern check it correctly and accurately, especially the: (1) Measurement and (2) Parts of pattern pieces; and then, cut the basic pattern following the cutting lines smoothly.

[← Back](#) [Next →](#)